



GIS IN ECOLOGY: ANALYZING RASTER DATA



Department of
Biological Sciences



UNIVERSITY OF
ALBERTA

Contents

Introduction.....	2
Tools and Functionality for Raster Data	2
Data Sources	3
Tasks.....	4
Getting Started.....	4
Creating Raster Data	6
Summary Statistics	9
Surface Analysis	10
Raster Modeling.....	11

This is an applied course on how to use the GIS software. It involves familiarizing you with the Spatial Analyst extension of ArcMap and teaching you the basic functions of spatial analysis using raster grids, including raster calculations, statistics, and overlays.

The following suggests some useful further reading:

www.esri.com/software/arcgis/extensions/spatialanalyst

www.ncgia.ucsb.edu/education/curricula/cctp/welcome.html

Also, the ESRI Virtual Campus Course on **Learning ArcGIS Spatial Analyst** is excellent:

www.biology.ualberta.ca/facilities/gis/index.php?Page=484#virtualcampus

References:

ESRI. 2013. What is Spatial Analyst? Online:

http://help.arcgis.com/en/arcgisdesktop/10.0/help/index.html#/What_is_the_Spatial_Analyst_extension/005900000001000000/

ESRI. 2013. Spatial Analyst Tutorials:

http://help.arcgis.com/en/arcgisdesktop/10.0/help/index.html#/About_the_ArcGIS_Spatial_Analyst_Tutorial/00nt00000002000000/

*GIS in Ecology is sponsored by the Alberta
Cooperative Conservation Research Unit
<http://www.biology.ualberta.ca/ac cru>*

GIS IN ECOLOGY: ANALYZING RASTER DATA

Introduction

The **raster data model** is useful for storing and analyzing GIS data that is continuous across an area. Example file types include grid coverages, satellite data, and scanned airphotos. Grids store continuous values and can represent derived data that are often used for analysis and modeling. Grids can be created from the **interpolation of sample points**, such as a surface of chemical concentrations in the soil, based on the **classification of an image**, such as for a land cover grid, or by **conversion of vector data**. Recall that the raster data model represents features as a surface divided into a regular grid of cells that have associated attribute value. Each cell is located by its row/column position from a known x, y coordinate and cell size. It excels in modeling continuous phenomena with gradually varying attributes.

Tools and Functionality for Raster Data

The **Spatial Analyst** extension provides powerful spatial analysis tools that allow you to:

- Create data: e.g. hillshade, slope, aspect, and contours
- Identify spatial relationships: e.g. distance and direction to water, population density over a region, association between aspect and survival of a plant species
- Find suitable locations: e.g. querying data or combine datasets
- Calculate the cost of travel: e.g. find the best route through a landscape

The various Spatial Analyst tools and functions are located in the Spatial Analyst toolbar and in ArcToolbox.

The functions are based on the geometric configuration of the raster data, the spatial coincidence of each cell, as well as on the attributes that they depict. For example, to multiply the cell values of two layers together depends on the location and the value of the cell counterparts on each layer. Within neighborhoods or zones, the analyses applied to cells rely on the spatial configuration of the neighborhood or zone as well as the cells and values in the configuration. They work on:

- Single cells (**Local** functions)
- Cells within a neighborhood (**Focal** functions)
- Cells within zones (**Zonal** functions)
- All cells within the raster (**Global** functions)
- Combined layers of cells to perform a specific application (**Application** functions – e.g. density, surface generation, surface analysis, hydrologic analysis, geometric transformation, generalization, and resolution altering)

Basically, the operators and functions work on a cell-by-cell basis, and calculations for each cell requires:

1. The value of the cell,
2. The manipulation of the operator or function that is being applied, and
3. Which other cell locations and their values need to be included in the calculation.

Every cell location in a raster has a value assigned to it, but if there is not enough information available for a cell location, it is assigned **Nodata**. Nodata and "0" are not the same because "0" is a valid value that is used in calculations. Nodata may be ignored or used to supersede all other values.

Data Sources

The data layers used in this short course have a scale of 1:20,000 and a spatial reference of NAD83 UTM Zone 11, with the map units in meters.

The following table summarizes the metadata for the Spray Lake dataset in the \COURSES\GIS-100\3_ARD folder:

Name	Description	Feature	Data Model
dem	digital elevation model – 25 m cell size	Grid	Raster
access	roads and trails		
avi	landcover and Alberta Vegetation Inventory attributes	Polygon	Vector
basin	watershed boundary excluding BNP	Polygon	Vector
rivers	streams and rivers	Line	Vector

Note: A Digital Elevation Model (DEM) is a special raster in which each cell (pixel) represents elevation values. The DEM used here is in 1-meter vertical intervals.

See “**What is raster data,**” “**About performing analysis in Spatial Analyst**” and “**NoData and how it affects analysis**” in ArcGIS Desktop Help for more information.


Tasks

Analysis options, reclassifying, converting, summary statistics, surface analysis, distance, raster modeling.

Getting Started

Setting the working environment:

1. COPY the “3_ARD” folder from [\\bio_print\Courses\GIS-100](#) to **C:\WorkSpace**
2. Start ArcMap by choosing START >>> PROGRAMS >>> ARCGIS >>> ARCMAP
3. Start using ArcMap with a new blank map
Enable the Spatial Analyst extension.
4. Choose CUSTOMIZE >>> EXTENSIONS
5. Click in the check box beside “Spatial Analyst” to ENABLE the extension
6. Click CLOSE



7. Click the ARCTOOLBOX WINDOW button to show it and dock where you wish
8. Change the name of the “Layers” data frame to: **“Spray Lake”**
9. ADD DATA layers from the **C:\Workspace\3_ARD** directory:
 - **SprayLake.gdb\dem**
 - **AVI.lyr, Basin.lyr, Rivers.lyr, and Access.lyr**

Setting the environment:

To control the area of analysis and output, you need to specify the working directory, extent, and cell size defaults you wish to use for your spatial analyses.

10. Right click on ArcToolbox
11. Choose ENVIRONMENTS
12. Expand WORKSPACE and set all workspaces to:
 - **C:\Workspace\3_ARD\Rasters.gdb**
13. Expand EXTENT and set
 - Extent: Same as layer **Basin**
 - Snap Raster: **dem**
14. Expand RASTER ANALYSIS and set the following:
 - Cell Size: Same as layer **dem**
 - Mask: **Basin**
15. Click OK

16. Click on SPATIAL ANALYST TOOLS to expand the listing of toolboxes available with the Spatial Analyst extension
10. Choose FILE >>> DOCUMENT PROPERTIES >>> DATA SOURCE OPTIONS to “Store relative pathnames”
11. Click OK
12. SAVE the map document; e.g. **SprayLake_todaysdate.mxd**

Creating Raster Data

Reclassifying:

Often you may want less complex information than what is provided by the original raster dataset. For example, suppose you want to depict elevation ranges instead of actual elevations. Reclassifying your data simply means replacing input cell values with new output cell values. The main reasons to do this include replacing values based on new information, scaling to new values, or grouping certain values together.

1. In ArcToolbox, SPATIAL ANALYST TOOLS >>> RECLASS >>> RECLASSIFY
 - Select **dem** as the Input raster
 - Select **VALUE** as the Reclass field
 - Click on CLASSIFY and select
 - a. Method: **NATURAL BREAKS**
 - b. Number of classes: **6**
 - c. Click OK
 - Type Output raster: **elevrange**
 - Click OK
2. Turn OFF **AVI** to view the raster layers beneath
3. Label and symbolize **elevrange** appropriately
4. **SYMBOLIZE dem** to look the same as **elevrange**

These two layers are not identical. dem consists of the original elevation values from 0 to 3158 meters and elevrange has actual class values from 1 to 6. You’ll look at the differences more closely below. Also, you may have noticed that elevrange has the extent of Basin – this is the effect of setting the raster analysis mask in the Environments.

Converting features to raster:

A common method of creating grid raster data is to convert vector features. When converting feature data to a raster, the output cell size you

specify is affected by: resolution of input data, output resolution needed to perform your analysis, and processing speed (note smaller cell size leads to larger rasters that require longer processing times). See ArcGIS Desktop Help for more information on cell size. When you convert polygons, cells are given the value of the polygon found at the center of each cell.

5. Open CONVERSION >>> TO RASTER >>> FEATURES TO RASTER
6. Enter the following:
 - Input features: **AVI**
 - Field: **LANDCOVER**
 - Output cell size: **25** (i.e. keep the default as set in Options above)
 - Output raster: **landcover**
 - Click OK
7. REPEAT the conversion of **AVI** to a new output raster named **moist_reg** using the **MOIST_REG** field
8. Turn all layers off except for AVI and landcover
9. Modify the symbology of AVI to show features as Single symbol with **Hollow** fill
10. Zoom-in along any of the polygon boundaries for a closer look

Notice the obvious difference in the boundary between the AVI vector and landcover raster data representations. This demonstrates the major disadvantage of raster representation, which is the loss of accuracy in spatial detail that results from the restructuring of vector data to fixed raster-cell boundaries.

11. Open the attribute tables for **AVI** and landcover
12. Review “**raster data**” topics in ArcGIS Desktop Help
13. Close tables and ZOOM TO FULL EXTENT
Modify the labels and color scheme within layer symbology.
14. Double click on **moist_reg** and select the SYMBOLOGY tab
15. Turn all layers OFF except for moist_reg
16. In the SYMBOLOGY tab: Show Unique Values for MOIST_REG
17. Select the Red-Green color scheme
18. Change the ‘x’ color symbol to GREY
19. Click in each of the LABEL cells and type in labels to reflect moisture regime classes as shown in the figure
20. Click OK

The legend for your layer has changed in the table of contents. Now, if you want to save a layer to disk, you can save everything about the

layer (symbology, labels, classification). This is very convenient because when the layer file gets added to another map document, it will draw exactly as it was saved. To keep the layer save as a layer file:

21. Right click on **moist_reg**
22. Click SAVE AS LAYER FILE
23. Navigate to **C:\WorkSpace\3_ARD**
24. Type directly to change the Label name
25. Click SAVE
26. In the SYMBOLOGY tab for **landcover**, click the IMPORT button
27. BROWSE to the **Landcover.lyr** file and click ADD to import symbology
28. Optionally, right click the name to SAVE AS LAYER FILE and replace the existing one with reference to the newly created raster

Selecting and identifying raster cells:

The IDENTIFY button can be used to click on any cell in your map and display the attributes associated with the cell in the Identify Results window. You cannot select single cells or regions interactively on the layer in the data frame, but you can select all cells having certain values by selecting the value(s) within the attribute table.

29. Right click on the grid name, OPEN ATTRIBUTE TABLE, and then click on the left button beside a value to highlight all cells having that value on the map – *the corresponding cells are highlighted in the view*
30. OPEN ATTRIBUTE TABLE for each of dem, elevrange, and moist_reg
31. Examine the structures of the various grid tables...

Required fields in a grid attribute table are value (the assigned numerical value) and count (the number of cells having the corresponding value).

The dem grid consists of cells that each contains an elevation value for its location and the count indicates how many cells have that elevation value. elevrange.

The moist_reg grid has an additional attribute field called MOIST_REG; this is because you converted from the polygon feature field of the same name. Since grids require a numerical value, ArcMap assigned integers to the text strings of MOIST_REG.

Summary Statistics

Spatial Analyst offers several functions to statistically analyze your data and create new information based on raster cell functions. In the following exercises you will learn where to access neighborhood and zonal statistics.

Neighborhood Statistics (Focal Functions):

Now you will calculate how many different types of landcover classes (variety) are found within a 275 X 275 m neighborhood (a.k.a. a moving window):

1. Open SPATIAL ANALYST TOOLS >>> NEIGHBORHOOD >>> FOCAL STATISTICS
 - Select **landcover** as the input raster
 - Specify **lc_variety** as the output raster
 - Select a **Rectangular** neighborhood
 - Click on MAP units
 - Enter **275** m in both the height and width boxes
 - Choose **VARIETY** as the statistics type
 - Click OK
2. Modify the SYMBOLOGY:
 - Show: Unique Values
 - Color Scheme: rainbow
 - Click OK
3. Right click on **lc_variety** to OPEN ATTRIBUTE TABLE

The table shows how many cells have a particular number of landcover classes within 275 X 275 meters of it. Which cells have the greatest number of classes surrounding them?

4. Select the table row and then examine the corresponding selected spatial data to see where these cells are – zoom in and alternately switch on/off landcover and lc_variety to view the data values
5. Click on the FULL EXTENT button
6. Choose SELECTION >>> CLEAR SELECTED FEATURES
7. Close the table when finished viewing

Zonal Statistics (Zonal Functions):

Suppose you want to identify how many vegetation types are in each elevation range class. This requires calculating statistics within a zone (two or more cells having the same value):

8. Open SPATIAL ANALYST TOOLS >>> ZONAL >>> ZONAL STATISTICS AS TABLE
 - Select **elevrange** as the zone dataset
 - Select **Value** as the zone field
 - Select **landcover** as the value raster
 - Type **ZonalSt_ellc** as the output table
 - Choose **ALL** as the chart statistic
 - Click OK

Zonal statistics calculates the selected statistics for the output table – even if they are not appropriate for the input data values!

9. Right click on the table (you may have to click on the List by Source view of the Table of Contents to find the table) and click OPEN

Which elevation zone has the greatest variety of landcover types? Which has the least? Inspecting the Min and Max fields when the Range is one or two indicates the landcover value... you may confirm the landcover name by opening the LANDCOVER attribute table.

10. Close the table when finished viewing

Surface Analysis

*Through surface analyses, you can derive new information from a raster DEM to identify specific patterns not readily apparent in the original surface, such as shaded relief (hillshade), angle of slope, aspect or the compass direction a slope faces, contours, and viewshed. First you will create a **hillshade** from the DEM to provide a shaded relief backdrop over which the LANDCOVER layer will be draped and made transparent to give you a good visual impression of the terrain.*

Hillshade:

1. Choose SPATIAL ANALYST TOOLS >>> SURFACE >>> HILLSHADE
 - Select **dem** as the input raster
 - Specify **hillshade** as the output raster
 - Leave all else at their defaults - refer to *ARCGIS DESKTOP HELP* for an explanation of each option
 - Click OK

The new temporary hillshade layer has been added to your map. You will now make the landcover layer transparent so the hillshade can be seen through it.

2. Turn all layers off except for **hillshade** and **landcover**

3. Adjust the drawing order so hillshade draws below landcover
4. Double click landcover to view layer properties
5. In the DISPLAY tab, type **50%** for Transparent
6. Click OK
7. Turn on the Rivers layer

The hillshade layer gives a vivid impression of the terrain underneath the landcover layer. This useful visualization tool shows how mountainous the Spray Lake watershed is. A slope surface analysis will further quantify this and locate the lowest slopes to use in the riparian zone modeling below.

8. SAVE the map document

Raster Modeling

This task involves steps to model riparian vegetation cover by using ModelBuilder (alternatively, you could use the Spatial Analyst toolbar GUIs, or access the tools individually through ArcToolbox). Riparian zones provide important habitat characteristics for many wildlife and plant species. Identifying the ecotone between aquatic and upland terrestrial environments requires more than simply mapping out proximity to water. The wetted perimeter of riparian habitat is also confined to low-slope terrain. You have already created landcover. You will complete the model by:

- Creating a new toolbox and model
 - Creating slope
 - Creating distance to rivers
 - Using map algebra to isolate riparian zone vegetation
1. Right click on ArcToolbox and choose ADD TOOLBOX
 2. Navigate to the 3_ARD folder and click the NEW TOOLBOX button
 3. Rename the Toolbox to "**ARD**"
 4. Right click on the **ARD** toolbox and choose NEW >>> MODEL

Note: All tools indicated below are found in ArcToolbox >>> SPATIAL ANALYST TOOLS.

Creating slope:

4. Expand the SURFACE toolset
5. Drag the SLOPE tool to the ModelBuilder window

6. Double click on the SLOPE tool element to access its parameters and specify the following:
 - Input raster: dem
 - Output raster: **Slope_dem**
 - Keep DEGREE and other defaults
 - Click OK

Creating distance to water:

Land that is further away from a source of water is less likely to be saturated enough to support riparian species, so calculate straight-line distances to rivers is in order.

7. Expand the DISTANCE toolset
8. Drag the EUCLIDEAN DISTANCE tool to the ModelBuilder window
9. Double click on the tool element to access its parameters
 - Input: **Rivers**
 - Output raster: **EucDist_rivers**
 - Keep all the defaults and click OK

Using map algebra to isolate riparian zone vegetation:

Map algebra involves mathematical calculations using operators and functions on input layers (grid datasets or raster layers, and even shapefiles, tables, constants, and numbers).

Several operators are available:

- *Arithmetic operators: *, /, -, +*
- *Boolean operators: And (also &), Or, Xor, Not*
- *Relational operators: ==, >, <, <>, >=, <=*
- *Mathematical functions: Logarithmic, Arithmetic, Trigonometric, and Powers*

*Use the **Raster Calculator** to weight and combine grids as part of a modeling process, to make selections on your data, and to apply mathematical operators and functions.*

Operators and functions evaluate the expression only for input cells that are spatially coincident with the output cell.

A Boolean overlay is one type of map algebra calculation that results in values of 1 (true) and 0 (false); it is useful for evaluating where riparian zones are true based on the following selection criteria:

- *Slopes <= 6 degrees*
- *Distance to rivers <= 100 meters*

Arithmetically combining the above Boolean expression to isolate riparian zones with the extracted vegetation cells will yield the desired output.

10. Expand the MAP ALGEBRA toolset
11. Drag the RASTER CALCULATOR tool to the ModelBuilder window
12. Double click on the tool element to access its parameters
13. Through a combination of typing and double-clicking the layer names, enter the following:

```
("%Slope_dem%" <= 6) *
("%EucDist_rivers%" <= 100) *
"landcover"
```

14. Enter **riparian** as the Output raster
Take a moment to understand what you have just entered. Note: Layers in the map document are indicated by double quotes; layers not yet created in the model are indicated by double quotes and percent symbols.

You have entered an expression that will multiply two raster grids – which each has cell values of 1 where their expressions are evaluated as true and all other cells with a value of zero where the expression is false – with each other and with the landcover values.

15. Click OK
16. Click the AUTO LAYOUT and FULL EXTNET buttons
17. In Model >>> Model Properties, provide a Name and Label
18. SAVE the model
19. VALIDATE the model
20. RUN the model
21. In ModelBuilder, right click on each of the Slope_dem, EucDist_rivers, and riparian output elements and choose ADD TO DISPLAY

22. CLOSE ModelBuilder
Inspect each of the intermediate and output layers more closely by symbolizing and examining the attribute tables. For example, symbolize so that all areas shown by white indicate slopes less than 6 degrees in the SLOPE_DEM layer and distances less than 100 meters in the DISTRIVER layer. This identifies where water is most likely to accumulate and soak along the riparian zone.

23. OPEN ATTRIBUTE TABLE for RIPARIAN
24. SAVE the map document

25. CHALLENGE: Calculate area, in hectares, (HINT: COUNT * cell size squared) for each landcover class (HINT: Join by attributes)